

Uploads and php.ini

Written by Trond

Wednesday, 10 March 2010 19:26 - Last Updated Sunday, 16 May 2010 19:38

If you have problems uploading files to your server, or if you have a problem with larger files, you may need to make some adjustments to the php.ini configuration.

Some hosts allow you to upload a php.ini file to your root folder. This is the preferred way to make the adjustments. If you can't use a local php.ini you can make the same changes in a apache .htaccess file.

Here you will find some info on the php.ini file.

You can download the php.ini at the bottom of this page.

The php.ini file contains all the configuration settings for your installation. Sometimes these settings might be overridden by directives in apache .htaccess files or even within the scripts themselves but for the moment let's just concentrate on the ini file.

This file contains the following settings that we need to modify:

- file_uploads
- upload_max_filesize
- max_input_time
- memory_limit
- max_execution_time
- post_max_size

The first one is fairly obvious if you set this off, uploading is disabled for your installation. We will cover the rest of the configuration settings in detail below.

upload_max_filesize and post_max_size

Files are usually POSTed to the webserver in a format known as 'multipart/form-data'. The post_max_size sets the upper limit on the amount of data that a script can accept in this manner. Ideally this value should be larger than the value that you set for upload_max_filesize.

Uploads and php.ini

Written by Trond

Wednesday, 10 March 2010 19:26 - Last Updated Sunday, 16 May 2010 19:38

It's important to realize that `upload_max_filesize` is the sum of the sizes of all the files that you are uploading. `post_max_size` is the `upload_max_filesize` plus the sum of the lengths of all the other fields in the form plus any mime headers that the encoder might include. Since these fields are typically small you can often approximate the upload max size to the post max size.

According to the PHP documentation you can set a `MAX_UPLOAD_LIMIT` in your HTML form to suggest a limit to the browser. Our understanding is that browsers totally ignore this directive and the only solution that can impose such a client side restriction is Rad Upload Applet

memory_limit

When the PHP engine is handling an incoming POST it needs to keep some of the incoming data in memory. This directive has any effect only if you have used the `--enable-memory-limit` option at configuration time. Setting too high a value can be very dangerous because if several uploads are being handled concurrently all available memory will be used up and other unrelated scripts that consume a lot of memory might effect the whole server as well.

max_execution_time and max_input_time

These settings define the maximum life time of the script and the time that the script should spend in accepting input. If several mega bytes of data are being transfered `max_input_time` should be reasonably high. You can override the setting in the ini file for `max_input_time` by calling the `set_time_limit()` function in your scripts.

The `php.ini` you can download below is optimized for common Joomla! 1.0.x installations. If you use a picture gallery with huge images or videos, you may need to adjust the `upload_max_filesize` and `post_max_size`

In Joomla!: `php.ini` must be placed both in `/root/` AND in `/root/administrator/`

[DOWNLOAD PHP.INI HERE](#)